

Department:
Document name:
Date:

Product Management
RN NPB1616 V2814.docx
3 June 2020



Neuron NPB1616S

What's new in version 2.8.14

Note

- IGMP leave and join timeout need to be set in the switch to minimum of 1 second
- When updating from another product to the NPB1616 software all settings will be defaulted.

Known issues

- Talkers/listeners s2022 could expose start-up issues
- 720p50 and 1080i50 Test patterns outputs black
- The output format Ref differences SD has an offset with respect to reference of 1 line and 300 pixels
- The output format Ref differences PTP 1080p50 has an offset with respect to reference of 80 pixels
- The output format Ref differences 720p60 has an offset with respect to reference of 1 line and 75 pixels
- PTP is drifting (NEU-495)
- Configuration of test pattern generator doesn't always work. Reboot board for a reset
- When the reference is instable, processing paths could stall